
Equil SDK for Windows

PNF

2015. 05

I. Concept

- Hardware Structure
- Software Structure
- Background knowledge

II. Development

- Project setting
- components of Library
- reference
- Guide

III. Design Guide

I. Concept

- Hardware Structure
- Software Structure
- Background knowledge

II. Development


- Project setting
- components of Library
- reference
- Topics

III. Design Guide


Concept > Equil Device


Model	Applicable Device	Connection	Writing	
Equil Smart Pen	iPhone,iPod,iPad Android Windows OS X	Bluetooth	On Any Paper	
Equil Smart Marker	iPhone,iPod,iPad Android Windows OS X	Bluetooth USB cable	On Any Whiteboard, Wall	

Concept > Hardware Structure (Equil Smart Pen)




Concept > Hardware Structure (Equil Smart Marker)





Concept > Background knowledge > Calibration

Calibration is Mapping the points of paper P1~P4 to coordinates T1~T4 (Pen Mode) TT1~TT4(Mouse Mode) of screen in order to have the image on the screen look the same as the image on the paper. In case of Equil, assuming that receiver is parallel with paper, just clicking two points(P1,P3) is enough.



➤ Refer to Serial Port Protocol communication

<http://support.microsoft.com/kb/823179>

I. Concept

- Hardware Structure
- Software Structure
- Background knowledge

II. Development

- Project setting
- components of Library
- reference
- Guide

III. Design Guide

IV. Go to App Store

1. copy PNFPenLib.dll into your folder where exe file exists.
2. Add PNFModule.vb in the sources into your project

Development > components of Test Sample (PenEx_VBDotNetVer)

Folder	File	Class	descript
\$PenEx_VBDotNetVer	PenEx_VBDotNetVer.vbproj		
	PenEx_VBDotNetVer.vbproj.user		
	Module1.vb	Module1	Definitions
	frmPenEx.vb	frmPenEx	Main form
	frmPenEx.Designer.vb	frmPenEx	
	frmPenEx.resx	frmPenEx	
	frmCalibration.vb	frmCalibration	Calibration Form
	frmCalibration.Designer.vb	frmCalibration	
	frmCalibration.resx	frmCalibration	
\$PenEx_VBDotNetVer/bin/Release	BTlib.dll		Library DLL
	cali_bg.png		Image for Calibration
	cali_num1.png		Image for Calibration
	cali_num2.png		Image for Calibration

※ \$(TestHome) : [unZipped folder]/ PenEx_VBDotNetVer

● Constants and APIs for Equil

Declared in	Module1.vb
-------------	------------

➤ Overview

Definitions of functions and constants for Pen Library

➤ Members

PenStatus			
Type	Enum Integer	Property	readonly
Description	PEN_DOWN : Pentip down PEN_MOVE : Move with Pentip down PEN_UP :Pentip up PEN_HOVER : Move with Pentip up		
Range	1 ~ 4		
Device	Equil Smart Pen / Marker		
Usage			

GestureMessage			
Type	Integer	Property	readonly
Description	GESTURE_CIRCLE_CLOCKWISE = 100 GESTURE_CIRCLE_COUNTERCLOCKWISE GESTURE_CLICK		
Range	100 ~ 102		
Device	Equil Smart Pen		
Usage			

WM_PENCONDITION			
Type	Integer	Property	readonly
Description	Message for environment variables of device.		
Range	&H400 + 3		
Device	Equil Smart Pen		
Usage			

WM_RETURNMESSAGE			
Type	Integer	Property	readonly
Description	Message for Pen Data		
Range	&H400 + 1		
Device	Equil Smart Pen / Marker		
Usage			

WM_GESTUREMESSAGE			
Type	Integer	Property	readonly
Description	Message for Pen Gesture		
Range	&H400 + 2		
Device	Equil Smart Pen		
Usage			

➤ APIs

FindPort()		
Description	It searches and connects all serial port devices in the registry sequentially. If it is valid port, start to communicate.	
Out	Void	
Input	N/A	
Device	Equil Smart Pen / Marker	
Usage	<pre>Public Sub ConnectPen() SetReciveHandle(m_ReciveHanle) SetDrawHandle(m_DrawHanle) End Sub</pre>	

SetDrawHandle(ByVal hWnd As System.IntPtr)		
Description	Define the object to receive pen data	
Out	Void	
Input	System.IntPtr	Window handle to receive pen data
Device	Equil Smart Pen / Marker	
Usage	<pre>Public Sub ConnectPen() SetReciveHandle(m_ReciveHanle) SetDrawHandle(m_DrawHanle) End Sub</pre>	

CheckConnect()		
Description	Where pen is connected or not	
Out	Boolean	True/False
Input	N/A	
Device	Equil	
Usage	<pre>Public Sub ConnectPen() SetReciveHandle(m_ReciveHanle) SetDrawHandle(m_DrawHanle) FindPort() ... bPenConnectExit = False bPenConnect = CheckConnect() Dim del As ConnectDelegate = New ConnectDelegate(AddressOf DelegateUISet) Me.BeginInvoke(del) bPenConnecting = False MouseFlagDisable() End Sub</pre>	

SetCalibMode(ByVal bCalibMode As Boolean)		
Description	Set pen mode or mouse mode. Pen mode is to receive Pen data only to target view. Mouse mode is to receive Pen data as mouse event.	
Out	Void	
input	Boolean	True : Pen Mode, False: Mouse Mode
Device	Equil Smart Pen	
Usage	If bPenConnect Then SetCalibMode(True) bPenRunning = True Else MessageBox.Show("Either device is off or not in good connection. Check device and try again. Or pair it again.") End If	

OnDisconnect()		
Description	Disconnect device. Close serial port.	
Out	Void	
Input	N/A	
Device	Equil Smart Pen / Marker	
Usage	OnDisconnect() bPenConnect = False MouseFlagDisalbe()	

SetCalibration_Top(ByVal pt As PointF)		
Description	Set P1(left top) coordinate of calibration	
Out	Void	
Input	PointF	P1 coordinate of calibration
Device	Equil Smart Pen / Marker	
Usage	<pre> If m_pRec.PenStatus = PenSatus.PEN_UP Then Select Case iPenCalibrationStatus Case PenCalibrationSatus.CAL_TOP iPenCalibrationStatus += 1 SetCalibration_Top(New PointF(m_pRec.X, m_pRec.Y)) pic1.Visible = False pic2.Visible = True Case PenCalibrationSatus.CAL_BOTTOM SetCalibration_Bottom(New PointF(m_pRec.X, m_pRec.Y)) SetCalibration_End() End Select End If </pre>	

SetCalibration_Bottom(ByVal pt As PointF)		
Description	Set P3(right bottom) coordinate of calibration	
Out	Void	
Input	PointF	P3 coordinate of calibration
Device	Equil	
Usage	<pre>If m_pRec.PenStatus = PenSatus.PEN_UP Then Select Case iPenCalibrationStatus Case PenCalibrationSatus.CAL_TOP iPenCalibrationStatus += 1 SetCalibration_Top(New PointF(m_pRec.X, m_pRec.Y)) pic1.Visible = False pic2.Visible = True Case PenCalibrationSatus.CAL_BOTTOM SetCalibration_Bottom(New PointF(m_pRec.X, m_pRec.Y)) SetCalibration_End() End Select End If</pre>	

SetCalibration_End()		
Description	Finish calibration	
Out	Void	
Input	N/A	
Device	Equil Smart Pen / Marker	
Usage	<pre>If m_pRec.PenStatus = PenSatus.PEN_UP Then Select Case iPenCalibrationStatus Case PenCalibrationSatus.CAL_TOP iPenCalibrationStatus += 1 SetCalibration_Top(New PointF(m_pRec.X, m_pRec.Y)) pic1.Visible = False pic2.Visible = True Case PenCalibrationSatus.CAL_BOTTOM SetCalibration_Bottom(New PointF(m_pRec.X, m_pRec.Y)) SetCalibration_End() End Select End If</pre>	

SetPenDownThreshold(ByVal iDown As Integer)		
Description	Set threshold of pen pressure for recognizing if pen tip is down * Default Value = 25;	
Out	Void	
Input	Integer	25 ~ 700
Device	Equil Smart Pen	
Usage	SetPenDownThreshold(TrackBar1.Value)	

SetAudio		
Description	Change Audio mode and volume of Smart Marker	
Out	Void	
Input	BOOL	Yes:/No
Device	Equil Smart marker	
Usage	SetAudio(CByte(CInt(txtAudioMode.Text)), CByte(CInt(txtAudioVolume.Text)))	

● _pen_rec Structure

Declared in	Module1.vb
-------------	------------

➤ Overview

_pen_rec is packet of pen data.

It is received every pen strokes and hovering through WM_RETURNMESSAGE message.

➤ Members

X, Y			
Type	Integer	Property	readonly
Description	Not calibrated coordinates		
Range	0 ~ 6500		
Device	Equil Smart Pen / Smart Marker		
Usage			

TX, TY			
Type	Integer	Property	readonly
Description	Calirated coordinates		
Range	According to the target view size		
Device	Equil Smart Pen / Smart Marker		
Usage			

PenStatus			
Type	Integer	Property	readonly
Description	Where pentip is pressed or not		
Range	PEN_DOWN : Pentip down PEN_MOVE : Move with Pentip down PEN_UP :Pentip up PEN_HOVER : Move with Pentip up (defined in PNFModule.vb)		
Device	Equil Smart Pen / Smart Marker		
Usage			

T			
Type	Integer	Property	readonly
Description	Temperature		
Range	0~60 ((Celcius))		
Device	Equil Smart Pen		
Usage			

P			
Type	Integer	Property	readonly
Description	Pressure		
Range	0 ~ 700		
Device	Equil Smart Pen		
Usage			

FUNC			
Type	Integer	Property	readonly
Description	Status of Pen button		
Range	0 ~ 1		
Device	Equil Smart Pen		
Usage			

IRGAP			
Type	Integer	Property	readonly
Description	IR Gap (only for firmware, SW dot not need to know)		
Range	0 ~ 3000		
Device	Equil Smart Pen		
Usage			

Sensor_dis			
Type	Integer	Property	readonly
Description	Distance between Ultrasonic sensors		
Range	Fixed by model		
Device	Equil Smart Pen		
Usage			

ModelCode			
Type	Integer	Property	readonly
Description	Model code.		
Range	Equil Smart Pen : 2 Equil Smart Pen 2 : 3 Equil Smart Marker : 4		
Device	Equil Smart Pen / Marker		
Usage			

HWVer			
Type	Integer	Property	readonly
Description	Version of Hardware of receiver and pen		
Range	> =0		
Device	Equil Smart Pen / Marker		
Usage			

MCU1			
Type	Integer	Property	readonly
Description	Version of MCU 1 of receiver and pen		
Range	> =0		
Device	Equil Smart Pen / Marker		
Usage			

MCU2			
Type	Integer	Property	readonly
Description	Version of MCU 2 of receiver and pen Smart Marker Firmware can be updated on windows.		
Range	>=0		
Device	Equil Smart Pen / Smart Marker		
Usage			

PenTiming			
Type	Integer	Property	readonly
Description	Pen Type of Smart Marker.		
Range	RED = 81 GREEN = 82 YELLOW = 83 BLUE = 84 PEN_UP = 15 PURPLE = 86 BLACK = 88 ERASER_CAP = 89 LOW_BATTERY = 90 BIG_ERASER = 92		
Device	Equil Smart Marker		
Usage			

Development > reference

bRight			
Type	Integer	Property	readonly
Description	Which side of receiver to be drawn		
Range	0 : Left side of receiver 1 : Right side of receiver		
Device	Equil Smart Pen / Smart Marker		
Usage			

Station_Position			
Type	Integer	Property	readonly
Description	Position of sensor		
Range	TOP = 1 LEFT =2 RIGHT=3 BOTTOM=4		
Device	Equil Smart Pen / Smart Marker		
Usage			

● _PENConditionData Structure

Declared in	Module1.vb
-------------	------------

➤ Overview

_PENConditionData is packet of environment data
It is received every 2 seconds through WM_PENCONDITION message.

➤ Members

modelCode			
Type	Integer	Property	readonly
Description	modelcode		
Range	Equil Smart Pen : 2 Equil Smart Pen 2 : 3 Equil Smart Marker : 4		
Device	Equil Smart Pen / Smart Marker		
Usage			

pen_alive			
Type	Integer	Property	readonly
Description	How much seconds has passed after pen is awoken. Pen will fall a sleep, if pen is not used for 600 seconds.		
Range	0~600		
Device	Equil Smart Pen / Smart Marker		
Usage			

battery_station			
Type	Integer	Property	readonly
Description	Battery status of sensor		
Range	0~100		
Device	Equil Smart Pen / Smart Marker		
Usage			

Development > reference

battery_pen			
Type	Integer	Property	readonly
Description	Battery status of Pen		
Range	0~100 : Smart Pen 0,100 : Smart Marker (Smart Marker has only two level as HIGH,LOW)		
Device	Equil Smart Pen / Smart Marker		
Usage			

StationPosition			
Type	Integer	Property	readonly
Description	Position of sensor		
Range	TOP = 1 LEFT =2 RIGHT=3 BOTTOM=4		
Device	Equil Smart Pen / Smart Marker		
Usage			

usbConnect			
Type	Integer	Property	readonly
Description	If connection is by USB or Bluetooth.		
Range	0: Bluetooth 1: USB		
Device	Equil Smart Smart Marker		
Usage			

➤ Overview

Create and initialize Connection

➤ Example

```
1.Set handle of object to receive message for pen data
   SetReciveHandle(Handle)
2. Set handle of form to draw
   SetDrawHandle(picMain.Handle)
3. Start to connect

   If FindDevice() Then    'find usb connetion (only for over F/W version 6)
   Else
       PortSearch()      'find BT Connection

   End If
4. Check if connection is successful.
   bPenConnect =CheckConnect()

   If bPenConnect Then
       bPenRunning = True
   Else
       MessageBox.Show("Either device is off or not in good connection. Check device and try again. Or pair it again.")
   End If
```

Example : Module1.vb, frmPenEx.vb

➤ Overview

Internally PNFPenLib is supposed to send message about Pen Moving to the object set by "SetReciveHandle" whenever the pen moves

➤ Example

```
1. Set handle to process pen data
   SetReciveHandle(Handle)
2. Process message of Pen
Protected Overrides Sub WndProc(ByRef m As System.Windows.Forms.Message)
    Select Case m.Msg
        Case WM_RETURNMESSAGE
            Select Case m_pRec.PenStatus
                Case PenStatus.PEN_DOWN
                    ....
                Case PenStatus.PEN_MOVE
                    ....
                Case PenStatus.PEN_UP
                    ....
                Case PenStatus.PEN_HOVER
                    ....
            End Select
        Case WM_PENCONDITION
            If m.WParam = 1 Then 'receiver power off
            ElseIf m.LParam = 2 Then 'pen power off
            End If
        Case Else
            MyBase.WndProc(m)
        End Select
    End Sub
```

Example source: frmPenEx.vb

➤ Overview

Pen coordinates is converted to screen coordinates by projective matrix which is set in the calibration view.

➤ Example

```
1. . create calibration controller
   Dim frmCali As New frmCalibration
2. set calibration controller as target view
   SetReciveHandle(frmCali.Handle)
   frmCali.ShowDialog()
3. after calibration, reset target handle.
   SetReciveHandle(Handle)
4. example
   If bPenConnect Then
       If m_bDraw Then
           m_bDraw = False
           Dim frmCali As New frmCalibration
           SetReciveHandle(frmCali.Handle)
           frmCali.ShowDialog()
           SetReciveHandle(Handle)
           m_bDraw = True
       Else
           Dim frmCali As New frmCalibration
           SetReciveHandle(frmCali.Handle)
           frmCali.ShowDialog()
           SetReciveHandle(Handle)
       End If
   End If
```

Example source: frmCalibration.vb, frmPenEx.vb

I. Concept

- Hardware Structure
- Software Structure
- Background knowledge


II. Development

- Project setting
- components of Library
- reference
- Guide

III.Design Guide


IV. Go to App Store

1. Screen Mode when it is out of the motion area



When the pen is out of range, it shows in red color. The shape of color is changeable, it lets the users know it is deviated

2. Show message when pen goes to sleep mode (Smart Pen only)




3. Tutorial- related to Hardware

The information below must be included in the manual


We can provide source files as .psd format in 9 languages(English, Spanish, French, German, Italian, Japanese, Chinese–Simplified, Chinese-Traditional, Korean)

Please refer to Tutorial_source (Attachment)

Do not use this device right after it was moved from cold place to warm place or vice versa.




External disturbance like sharp metal noises, winds from heater or air conditioner, PDP TV, and/or external infrared rays may cause product malfunction.
(You can correct mistakes using undo/eraser)




Pen refill is replaceable .


Notice!




The receiver must be balanced and clipped onto the top center of the paper.



The light and sound sensors should be facing towards the workspace.



The receiver must not move while in use. clip the receiver on more than 2 pages of papers is recommended.




It may not operates within 2 cm from the receiver.

Pen instructions




1 Using a magnetic clip on the bottom of the receiver, attach the receiver to the top center of the paper.

Turn off the receiver first.



2 Press and hold the receiver power button until the blue LED light is turned on and blinks fast.



3 Go to 'Setting' > Bluetooth, find the device Equil-xxxxxx and connect to it. (After that, it will connect automatically)

※ iPhone 5S and iPhone 5c with iOS7.0.3 and later, automatic connection for Bluetooth is not available at the moment. users should manually connect Equil Smartpen to your device whenever turning on the receiver.

4 ▶ Run the application to use the pen.